Autodesk ACP-01101

Autodesk Certified Professional in AutoCAD for Design and Drafting



For More Information - Visit link below:

https://www.examsboost.com/


Product Version

- ✓ Up to Date products, reliable and verified.
 - ✓ Questions and Answers in PDF Format.

Latest Version: 7.0

Question: 1

Exhibit



This image needs to be reproduced in AutoCAD. The wall and plaster lines need to be on separate layers.

After drawing the top wall line on the wall layer, then selecting it, what two options in the Offset (OFFSET) command should be used to offset and place the resulting lines on the plaster layer? (Choose two.)

- A. Specify Offset Distance
- B. Select Current
- C. Select Object
- D. Select Layer

Answer: AD

Explanation:

The offset command is used to create parallel lines, concentric circles, and parallel curves1. To use the offset command, you need to specify the offset distance and select the object that you want to offset23.

Question: 2

You are modifying an AutoCAD drawing for a customer.

You would like to bring your customers attention to a specific area of the drawing that you modified for

review.

Which type of object is conventionally used?

- A. A viewport
- B. A construction line
- C. A solid hatch
- D. A revision cloud

Answer: D

Explanation:

The type of object that is conventionally used for this purpose is D. A revision cloud 123. A revision cloud

is a way to highlight changes or revisions in a drawing by creating a cloud-shaped polyline around them12. You can create a revision cloud by moving the mouse or by converting existing objects2. You can

also change the style, color, layer and properties of the revision cloud13.

Question: 3

DRAG DROP

Move three applicable xref options from the list on the left to the corresponding functions on the right Xref options may be used once or not at all. (Select 3)

Xref Options	Answer area	
Bind		Removes the xref drawing from the host drawing permanently and erases all instances of the xref drawing.
Detach		Retrieves the xref drawing and displays the most recently saved version of the drawing.
Reload		Converts the xref drawing into a block, making the drawing a permanent part of the host drawing.
Unload		
Xref Type		

Answer:

Xref Options	Answer area	
Bind	Detach	Removes the xref drawing from the host drawing permanently and erases all instances of the xref drawing.
Detach	Reload	Retrieves the xref drawing and displays the most recently saved version of the drawing.
Reload	Bind	Converts the xref drawing into a block, making the drawing a permanent part of the host drawing.
Unload		
Xref Type		

Explanation:

Removes the xref drawing from the host drawing permanently and erases all instances of the xref drawing. = Detach

https://knowledge.autodesk.com/support/autocad/learnexplore/

caas/CloudHelp/cloudhelp/2020/ENU/AutoCAD-Core/files/GUID-70599862-DF52-4291-B64B-8A4C45599F39-htm.html

Retrieves the xref drawing and displays the most recently saved version of the drawing. = Reload https://knowledge.autodesk.com/support/autocad/learnexplore/


caas/CloudHelp/cloudhelp/2020/ENU/AutoCAD-Core/files/GUID-70599862-DF52-4291-B64B-8A4C45599F39-htm.html

Converts the xref drawing into a block, making the drawing a permanent part of the host drawing. = Bind

https://knowledge.autodesk.com/support/autocad/learnexplore/caas/CloudHelp/cloudhelp/2020/ENU/AutoCAD-Core/files/GUID-70599862-DF52-4291-B64B-8A4C45599F39-htm.html

Question: 4

Refer to the exhibit.



When working on this part created with AutoCAD solids, the dimensions of the shaded planes need to be established.

Which U'CS shows the correct size and shape of the shaded planes?

- A. Face
- B. Vertical
- C. World
- D. View

Answer: A

Explanation:


The UCS is a moveable Cartesian coordinate system that establishes the XY work plane, horizontal and

vertical directions, axes of rotation, and other useful geometric references1. You can change the UCS origin and orientation for convenience as you specify points, enter coordinates, and work with drawing aids1.


The face option sets a new UCS based on a selected face of a 3D solid object2. This option will align the XY plane of the UCS with the selected face and show its correct size and shape2.

Question: 5

You have three multileaders as shown in exhibit 1. (Refer to the exhibit 1 tab.)



You need to change the display of the multileaders to match the multileaders in exhibit. (Refer to the exhibit 2 tab.)



Which command should you use?

- A. Align Leader
- B. Collect Leader
- C. Remove Leader
- D. Add Leader

Answer: B

Explanation:

The command that you should use is B. Collect Leader1. The collect leader option groups multiple leaders into one multileader object with a common landing line1. This option is useful when you want to create a single label or callout for multiple objects2.

To use this option, you need to select the MLEADER command and then select Collect Leader from the Options menu. Then you can select two or more existing multileaders that have similar properties and press Enter. The selected multileaders will be collected into one multileader object with a common landing line1.

Thank You for Trying Our Product

For More Information – Visit link below:

https://www.examsboost.com/

15 USD Discount Coupon Code:

G74JA8UF

FEATURES

- ✓ 90 Days Free Updates
- **✓** Money Back Pass Guarantee
- ✓ Instant Download or Email Attachment
- ✓ 24/7 Live Chat Support
- **✓** PDF file could be used at any Platform
- ✓ 50,000 Happy Customer

