

# **CyberArk**

## **CPC-CDE-RECERT**

**CyberArk CDE-CPC Recertification**



**For More Information – Visit link below:**

**<https://www.examsboost.com/>**

### **Product Version**

- ✓ Up to Date products, reliable and verified.
- ✓ Questions and Answers in PDF Format.

# Latest Version: 6.0

## Question: 1

You are planning to configure Multi-Factor Authentication (MFA) for your CyberArk Privilege Cloud Shared Service.

What are the available authentication methods?

- A. LDAR RADIUS. SAML OpenID Connect (OIDC)
- B. Windows. PKI. RADIUS. CyberArk, LDAP. SAML. OpenID Connect (OIDC)
- C. Privilege Cloud Shared Services fully utilize CyberArk Identity and its MFA options.
- D. Only RADIUS can be used to achieve MFA across all components, such as PSM for RDP and PSM for SSH.

**Answer: C**

Explanation:

<https://docs.cyberark.com/privilege-cloud-standard/latest/en/content/privilege%20cloud/privcloud-configure-auth.htm>

## Question: 2

When installing the first CPM within Privilege Cloud using the Connector Management Agent, what should you set the Installation Mode to in the CPM section?

- A. Active
- B. Passive
- C. Default
- D. Primary

**Answer: A**

Explanation:

When installing the first CyberArk Privilege Management (CPM) instance in the Privilege Cloud using the Connector Management Agent, the installation mode should be set to "Active". This configuration sets the CPM to be actively involved in password management and task processing without being in a standby or passive mode. Here are the step-by-step details:

This setup ensures that the CPM is immediately active and capable of handling requests without waiting for manual intervention or failover.

Reference: CyberArk's official documentation provides guidance on setting up the CPM, where it specifies the modes and their purposes.

## Question: 3

CyberArk User Neil is trying to connect to the Target Linux server 192.168.1.164 using a domain user ACME\linuxuser01 on domain acme.corp using PSM for SSH server 192.168.65.145. What is the correct syntax?

- A. `ssh neil@linuxuser01:acme.corp@192.168.1.164@192.168.65.145`
- B. `ssh neil@linuxuser01#acme.corp@192.168.1.164@192.168.65.145`
- C. `sshneil@linuxuser01@192.168.1.164@192.168.65.145`
- D. `ssh neil@linuxuser01@acme.corp@192.168.1.164@192.168.65.145`

**Answer: B**

Explanation:

In CyberArk Privilege Cloud, when connecting to a target server using the Privileged Session Manager (PSM) for SSH, the correct syntax for the SSH command includes the following format: `ssh neil@linuxuser01#acme.corp@192.168.1.164@192.168.65.145`. This syntax breaks down as follows: This specific format ensures that the CyberArk Privileged Access Manager correctly interprets and routes the connection through the PSM for SSH to the intended target server.

CyberArk Privilege Cloud Introduction

CyberArk Privileged Access Manager

CyberArk Privilege Cloud - Manage Safe Members

CyberArk Security Fundamentals

### Question: 4

After a scripted installation has successfully installed the PSM, which post-installation task is performed?

- A. The screen saver for the PSM local users is disabled.
- B. A new group called PSMSHadowUsers is created.
- C. The PSMAAdminConnect user password is reset.
- D. Remote desktop services are installed.

**Answer: A**

Explanation:

After the successful scripted installation of the Privileged Session Manager (PSM), one of the post-installation tasks is to disable the screen saver for the PSM local users. This is done to ensure that the PSMConnect and PSMAAdminConnect users, which are created during the installation process, do not have a screen saver activated that could interfere with the operation of the PSM.

CyberArk documentation on PSM post-installation tasks<sup>1</sup>.

CyberArk documentation on disabling the screen saver for PSM local users

### Question: 5

DRAGDROP:

Arrange the steps to install passive CPM using Connector Management in the correct sequence

### Unordered Options

|                                                                |
|----------------------------------------------------------------|
| Run the Connector Management Connector installer.              |
| When prompted to select the CPM mode, select Passive.          |
| When prompted to select the components to install, select CPM. |
| Install the CPM and optionally PSM, if required.               |

### Ordered Response

|  |
|--|
|  |
|--|

**Answer:**

### Unordered Options

|                                                                |
|----------------------------------------------------------------|
| Run the Connector Management Connector installer.              |
| When prompted to select the CPM mode, select Passive.          |
| When prompted to select the components to install, select CPM. |
| Install the CPM and optionally PSM, if required.               |

### Ordered Response

|                                                                |
|----------------------------------------------------------------|
| Run the Connector Management Connector installer.              |
| Install the CPM and optionally PSM, if required.               |
| When prompted to select the components to install, select CPM. |
| When prompted to select the CPM mode, select Passive.          |

Explanation:

1-Run the Connector Management Connector installer

2-Install the CPM and PSM

3-When you are prompted to select the components to install, select CPM.

4-When you are prompted to select the CPM mode, select Passive.

<https://docs.cyberark.com/ispss-deployment/latest/en/content/privilege%20cloud/privcloud-cpm-dr-install-config.htm>

# Thank You for Trying Our Product

For More Information – **Visit link below:**

**<https://www.examsboost.com/>**

15 USD Discount Coupon Code:

**G74JA8UF**

## FEATURES

- ✓ **90 Days Free Updates**
- ✓ **Money Back Pass Guarantee**
- ✓ **Instant Download or Email Attachment**
- ✓ **24/7 Live Chat Support**
- ✓ **PDF file could be used at any Platform**
- ✓ **50,000 Happy Customer**



Visit us at: <https://www.examsboost.com/test/cpc-cde-recert>